

Remove

Last Modified



software MANAGER

1. Remove Centero Software Manager Client

1. Go to **Control Panel\Programs\Programs and Features**, select **Centero Software Manager** and uninstall it.



2. Remove Centero Agent

Warning!

If other Centero products (like Centero Carillon) is installed, **do not** remove Centero Agent!

1. Go to **Control Panel\Programs\Programs and Features**, select **Centero Agent** and uninstall it.



SOFTWARE MANAGER

3. Remove Windows Update settings

1. Make sure that the `HKEY_LOCAL_MACHINE\SOFTWARE\Policies\Microsoft\Windows\WindowsUpdate` registry key is empty

→/ **Note!**

Windows Update client will revert to settings specified on local device. If you need you can use GPO or registry editor to specify desired Windows Update client settings so that user of the device cannot change settings from operating system UI.